


## How to use E-solution Manual Update File

**Note.** Manual update file is an .exe file. For Windows standard user, they may need a permission by Administrator to execute the files.

### 1. Check your e-solution current ver.

- (1) Open e-solution software on your PC.
- (2) Click on "Help" from pull down menu and select "About".


For the user with e-solution version 3.8.1, please use the manual update file 3.8.1 to 3.9.0




- (3) Close E-solution program.

## 2. Install the manual update files

(1) Find the manual update file from MHAIE website: <https://mhiae.com/e-solution/>




(2) Go down the same page so you can see E-solution manual update




(3) Click on "Download automatic update file v3.8.1 to v3.9.0" to start the download

(4) Run the .exe file

(5) Pop-up window for manual update software licence agreement will appear, click "Accept".




(6) Window below will appear



**Note.** For the manual update to be successful, it is important to select the correct destination folder where current e-solution is installed).


(7) Click "Install"

(8) Window below will appear, when installation is completed, window will close



### 3. Check e-solution updated ver.

- (1) Open e-solution
- (2) Click on "Help " → "About"



- (3) Window below will be shown with version 3.9.0 when the manual update is successful



### 4. Update folder permission in ver.3.9.0

E-solution software needs to allow the Windows user to full access to the files of the software. Ver 3.9.0 has a function to give permission to all the user to access the file, because some Windows user are restricted to access the files due to local security setting.

**Please make sure to activate "Update folder permission" from the pull down menu, after installation of ver3.9.0**

DOS window will be shown and permission to access the file will be updated.

